

Instruction to include sdl header file:

- Open gz archive and there should be a *.tar archive inside.
Open the *.tar and there should be a folder inside of that.
Copy that folder anywhere you like.
- Start up Code:Blocks and go to the Compiler and Debugger settings.
- Go to the Compiler tab under Search Directories. Click add. Then add in the include directory from the SDL folder you extracted.
- Then under the linker tab add in the lib directory from the SDL folder.
- Now take the SDL.dll from the SDL folder you extracted (it should be inside the bin subfolder) and copy it to where you're going to make your project. You're going to put SDL.dll in the same directory as your exe when you compile it.

Alternatively, you can copy SDL.dll to C:\WINDOWS\SYSTEM32 so your SDL app will find SDL.dll even if it's not in the same directory. If you're using a 64bit version of Windows, you'll want to put the dll in C:\Windows\SysWOW64.

The problem with this method is if you have multiple SDL apps that use different versions of SDL, you'll have version conflicts. If you have SDL 1.2.8 in SYSTEM32 when the app uses 1.2.13 you're going to run into problems. Generally you want to have your SDL.dll in the same directory as your executable developing and you'll **always** want to have SDL.dll in the same directory as the exe when distributing your app.

- Now start up Code::Blocks and create a new empty project.
- Then save the project where ever you want.
- Next, go to the project -> properties.
- Under the Build Targets tab, set Type to "GUI application". This is to make sure a console window does not pop up.
- Go to the Compiler and Debugger settings again and under the Linker Settings tab paste:

-lmingw32 -lSDLmain -lSDL

in Other Linker Options

- Add a new source file to the project with the following code:

```
#include "SDL/SDL.h"
```

```
int main( int argc, char* args[] )
{
    //Start SDL
    SDL_Init( SDL_INIT_EVERYTHING );

    //Quit SDL
    SDL_Quit();

    return 0; }
```

- Save the source and compile your project. If there are no errors, you're done. Otherwise go back and make sure everything is done. Double check that you have SDL.dll in the same directory as your exe or system32.
- In case of any problem go to http://lazyfoo.net/SDL_tutorials/.